

PBS to Slurm Migration

Quick reference for users migrating from the old PBS/Torque system to Slurm.

Command Equivalents

PBS/Torque	Slurm	Description
<code>qsub job.sh</code>	<code>sbatch job.sh</code>	Submit a job
<code>qsub -I</code>	<code>srunch --pty bash</code>	Interactive session
<code>qstat</code>	<code>squeue</code>	View jobs
<code>qstat -u username</code>	<code>squeue -u username</code>	Your jobs
<code>qdel JOBID</code>	<code>scancel JOBID</code>	Cancel a job
<code>pbsnodes</code>	<code>sinfo</code>	Node status
<code>qstat -f JOBID</code>	<code>scontrol show job JOBID</code>	Job details

Directive Equivalents

PBS/Torque	Slurm	Description
<code>#PBS -N name</code>	<code>#SBATCH --job-name=name</code>	Job name
<code>#PBS -q queue</code>	<code>#SBATCH --partition=partition</code>	Queue/partition
<code>#PBS -l nodes=1:ppn=8</code>	<code>#SBATCH --nodes=1 --cpus-per-task=8</code>	Nodes and cores
<code>#PBS -l mem=4gb</code>	<code>#SBATCH --mem=4G</code>	Memory
<code>#PBS -l walltime=02:00:00</code>	<code>#SBATCH --time=02:00:00</code>	Wall time
<code>#PBS -o output.log</code>	<code>#SBATCH --output=output.log</code>	Output file
<code>#PBS -e error.log</code>	<code>#SBATCH --error=error.log</code>	Error file
<code>#PBS -M email</code>	<code>#SBATCH --mail-user=email</code>	Email
<code>#PBS -m abe</code>	<code>#SBATCH --mail-type=ALL</code>	Mail events
<code>#PBS -V</code>	<code>#SBATCH --export=ALL</code>	Export environment
<code>#PBS -t 1-10</code>	<code>#SBATCH --array=1-10</code>	Job array

Environment Variables

PBS/Torque	Slurm	Description
<code>\$PBS_JOBID</code>	<code>\$SLURM_JOB_ID</code>	Job ID
<code>\$PBS_JOBNAME</code>	<code>\$SLURM_JOB_NAME</code>	Job name
<code>\$PBS_NODEFILE</code>	<code>\$SLURM_JOB_NODELIST</code>	Node list
<code>\$PBS_ARRAYID</code>	<code>\$SLURM_ARRAY_TASK_ID</code>	Array task ID
<code>\$PBS_NP</code>	<code>\$SLURM_NTASKS</code>	Number of tasks
<code>\$PBS_O_WORKDIR</code>	<code>\$SLURM_SUBMIT_DIR</code>	Submission directory

Key Differences

- Slurm requires `--account` and `--qos` — run `check_my_partitions` to find yours
- Slurm uses `--cpus-per-task` instead of `ppn`
- Memory in Slurm is per-CPU (`--mem-per-cpu`) or total (`--mem`)
- Slurm does not automatically change to the submission directory — add `cd` `$SLURM_SUBMIT_DIR` to your script if needed

Created 2026-06-14 08:41:00 UTC by levk

Updated 2026-06-14 08:41:25 UTC by levk